

Muquit Counter

About the Counter

The Muquit Counter is a program installed on the server that allows you to set up page counters and countdowns on your web pages. The Muquit Counter program is located at:

<http://www.yourdomain.com/cgi-bin/shr/counter/Count.cgi>

To insert a counter on a page, simply enter the following HTML tag:

```

```

The counter stores all count values and data in a central database and will automatically initiate a counter for you upon recognition of this tag. By default, the counter does not increment when a visitor presses the refresh button.

Display Features

The program accepts a wide array of variables that enable you to modify the way the counter is displayed. Variables are included in the counter HTML tag, as a **query string**. A query string is simply a set of variable names and values, initiated by the question mark character (?) and separated by the ampersand (&). For example:

```

```

Display Method

There are two key ways one can display a counter. These include via image templates and true type fonts.

Image Templates

Firstly, one can use a set of image templates. There are nine image templates currently available. They are:

Style A (Default)	
Style B	
Style C	
Style D	
Style E	

Style cd	0123456789:AMPM,-DHMS
Style cdr	0123456789:AP,-DHMS
Style cdd	
Style bang	୦୧୨୩୪୫୬୭୮୯:AMPM,-DHMS

To use one of the above styles, use the `dd` variable in the query string:

```

```

would render the counter using style D, while

```

```

would render the counter using style bang.

True Type Fonts

The second way to display a counter is through using true type fonts, or TTF files. TTF is the format used to store fonts on both PC and Macs. We can upload any TTF file to the server and allow you to "tap into it" using your counter. Currently the following fonts are available for use:

- arial.ttf
- times.ttf
- trebuchet.ttf
- verdana.ttf
- comic.ttf

To use one of these fonts for your counter, use the `font` variable in the query string:

```

```

would render your counter using the Comic Sans MS font.

The advantage to using TTF files for your counter is that you can easily change the size and color variations of it. For example:

```

```

would set the foreground color (text color) of your counter to white, the background color of your counter to black, and the font size to pt 25. Remember, the counter uses hexadecimal codes to determine color.

As new TTF files can be simply uploaded to the server for use, should you have such a file you would like to use for your counter please contact us.

Other Options

There are dozens of additional options ranging from borders to transparency colors. There are also ways to set up a countdown to a specific date. To view the complete set of options available, visit:

<http://www.muquit.com/muquit/software/Count/Count2.6/Count2.6/options.html>

To view a list of example counters, check out:

<http://www.muquit.com/muquit/software/Count/Count2.6/Count2.6/examples.html>

Updating Counter Values

In order to reset your counter, or initialize it at a certain value, please contact us.